

Article ID: 02032014-DB/KA-01

# How to Import/Export Sapphire<sup>™</sup> 7" Touch Screen **Configuration Files**

Sapphire Touch Screen (Cat. No. TS007-000/TS007-V00) Date: February 3, 2014 Summary: This article describes the process of importing and exporting configuration files to the Sapphire touch screen from a USB drive.

#### Information:

**Product:** 

#### 1. Access the Administration Menu

Press and hold Date/Time on the Sapphire Touch Screen interface to load the Settings • Menu

Front of House Cafeteria	Kitchen Multi-Purp	ose
Lighting	Accent On/Off	Guide On/Off
Performance	Performance	Performance
General	General	General
	Dec 13, 2013, 2:08:18 pm 🗲	



• Press Sign In to access the Import/Export configuration to display the Username/Password window

Sapphire Settings	
Set Time	Import Configuration
Network Configuration	Export Configuration
Edit Mode	Export Logs
Project Settings	Update Login Credentials
Software Version	Sign in
	Exit

• To access the import/export configuration functions you must be logged in as an administrator. Touch either the Name or Password fields to access the on-screen keyboard.

Set Time	Import Configuration
📄 🔔 Please Enter Userna	ame/Password:
Name:	
Password:	
ОК	Cancel



Enter the default Username & Password (may be different if you've changed on your . system) and press OK.

> Username: administrator Password: 1234

Sapphire Se	Please Enter Username/Password:
	Name: ad
	Password:
	OK Cancel
	Project Settings Update Login Credentials
q w	ertyuiop
a	sd f g h j k l
<u>+</u>	z x c v b n m 🔩
?123	, Next

The Full Settings menu will now display •

Sapphire Settings	
Set Time	Import Configuration
Network Configuration	Export Configuration
Edit Mode	Export Logs
Project Settings	Update Login Credentials
Software Version	Sign out
	Exit

Leviton Mfg. Co., Inc. Lighting & Energy Solutions 20497 SW Teton Avenue, Tualatin, OR 97062 1-800-736-6682 Tech Line: 1-800-959-6004 Fax: 503-404-5594 www.leviton.com/les © 2014 Leviton Manufacturing Co., Inc. All rights reserved. Subject to change without notice.



## 2. Import Configuration Data

• Insert a USB drive into the USB connection on the Sapphire Touch Screen



Press Import Configuration on the settings menu to display the system import window





• Select the file to import by pressing the arrow



• A list of all Sapphire Studio project files will display

Sapphire Settings	
sapphireUX-g4.zip	۲
sapphireUX-sports.zip	O
sapphireUX-UI Tour.zip	Ô
sapphireUX_20131213_090921.zip	0
sapphireUX-1to12cfnf.zip	Ô
sapphireUX-1to12cf.zip	Ô

Select the file to import



- Confirm the selected file is correct and Press OK. If it is not the correct file either press the arrow to view the list of files or press cancel to return to the menu.
- A progress bar shows the progress of the import, if needed press cancel to stop importing

# LEVITO



The progress bar window will close once the import has completed successfully, the • new user interface is now loaded

Sapphire Settings	
Set Time	Import Configuration
Network Configuration	Export Configuration
Edit Mode	Export Logs
Project Settings	Update Login Credentials
Software Version	Sign out
	Exit

Press exit to view the newly loaded user interface •

## 3. Export Configuration Data

Press Export Configuration from the settings menu

Sappine	settings	
	Set Time	Import Configuration
	Network Configuration	Export Configuration
	Edit Mode	Export Logs
	Project Settings	Update Login Credentials
	Software Version	Sign out
		Exit

Leviton Mfg. Co., Inc. Lighting & Energy Solutions 20497 SW Teton Avenue, Tualatin, OR 97062 1-800-736-6682 Tech Line: 1-800-959-6004 Fax: 503-404-5594 www.leviton.com/les © 2014 Leviton Manufacturing Co., Inc. All rights reserved. Subject to change without notice.



• A progress bar window will display showing the progress of the file export



- The file writes to the USB drive using the same file name that it was imported with, if the original configuration files is on the USB drive it automatically overwrites the file. If you need to stop the configuration export, press Cancel.
- When export is complete a system export message will display, press OK to return to the settings menu

Intwork Confin	stlon	6 13
System E>	port	
Export suc	cessfully completed	
	OK	
		_

- Remove the USB drive and update any copies of the configuration file as needed
- **Contact:** For questions or concerns, please call LES Technical Support at (800) 959-6004.